## **RET Options with Description**

Last Modified on 07/17/2025 3:17 pm EDT

| #  | RET Options                                 | Defaults | Description  |
|----|---|----------|--|
| 1  | Check Odor                                  | Υ        | Leave default.   |
| 2  | Contract-Allow Driver to<br>Select          | Υ        | Drivers can choose to apply deliveries to an active contract at the contract price or deliver outside the contract, which will use the daily price.  |
| 3  | Contracts-Auto Apply Overage                | Υ        | Leave default.   |
| 4  | Pre Shift Inspection                        | Υ        | An option to enable a Pre-Shift Inspection form, requiring the driver to confirm that the vehicle's condition is satisfactory at the start of the shift.   |
| 5  | End Shift Inspection                        | Y        | An option to add a <b>Truck Inspection</b> button to the <i>End Shift</i> screen, allowing drivers to perform an inspection.  Completion of the inspection is not mandatory.                     |
| 6  | Display Alternate Customer ID               | N        | Display the Alternate Customer ID in place of the Energy Force customer #.   |
| 7  | Use Preprinted paper                        | Υ        | Leave default.   |
| 9  | Purge Old Trip Reports                      | Υ        | Leave default.   |
| 10 | Archive trips for 30 days                   | Υ        | Leave default.   |
| 11 | Don't Print Price on ticket                 | Υ        | Leave default.   |
| 12 | Print Beg & End % on invoice                | N        | Begin and End % will show on invoice.  Note: RET Option #13 has to be set to N.  |
| 13 | Print Ending percent Only                   | Υ        | Ending % will print on the invoice under the sale # and tank name.  Note: Setting both Options 12 and 13 to N will exclude the percentage from being printed.                                    |
| 14 | Allow driver to change price                | Υ        | Driver ability to modify <i>Price</i> on <i>Invoice</i> screen.  |
| 15 | Allow driver to change tank name            | Υ        | Driver ability to modify Tank Name on Tank screen.   |
| 16 | Allow driver to change directions           | Υ        | Driver ability to modify <i>Directions</i> on <i>Tank</i> screen.  |
| 17 | Allow driver to change special instructions | Y        | Driver ability to modify Special Instructions on Tank screen.  |
| 18 | Allow drivers to add comment                | Y        | Allows drivers to add a comment, which will be sent to Energy Force as a driver tickler tied to the tank. Setting this option to N removes the Add Comment button from the Tanks / Notes screen. |

|    |  |    | Trigger the Out of Gas form to automatically appear when   |
|----|--|----|--|
| 19 | Trigger Out of Gas if zero percentage? | Υ  | the starting percentage is zero, requiring the driver to fill it   |
|    |  |    | out. It is recommended to be set as N for Refined Fuels and  |
|    |  |    | Cylinder Exchange truck computers.   |
| 20 | Default Ending Percentage to           | N  | The ending % will populate 99 in the <i>Invoice</i> screen; used in  |
| 20 | 99                                     | IN | refined fuels.   |
|    | Allow credit card payments             | N  | An option that allows drivers to accept credit card  |
| 21 |  |    | payments. By default, drivers can only accept cash or check  |
|    |  |    | unless option 40 is disabled for all payment methods.  |
| 22 | Turn off GPS point collection          | N  | An option to disable GPS point collection during the   |
|    |  |    | invoicing process.   |
| 23 | Price Zones active for HH?             | N  | Not Currently in Use.  |
| 24 | Differential Pricing active for HH?    | N  | Not Currently in Use.  |
| 25 | IP Address for HH to transmit to       |    | Leave default.   |
| 26 | Use Multi-Delivery Screen?             | Υ  | Allows the delivery to multiple tanks on a single ticket.  |
|    | Print Delivery Specific taxes?         | N  | The Energy Force tax description for applicable taxes will   |
| 27 |  |    | appear under the Sale Number and Tank Name, and above  |
|    |  |    | the ending percentage on the Invoice.  |
| 28 | Allow NonPumpable products?            | N  | Enables the <b>Product Delivery</b> button in the <i>Delivery</i> screen,                                      |
|    |  |    | this should always be <i>N</i> .   |
|    | Manifests?                             | Ν  | An option to print a manifest listing Products by Gallons,   |
| 29 |  |    | based on what is Loaded, Unloaded, and Sold during the   |
|    |  |    | shift. A manifest will be printed at the start of the shift and for each load and unload throughout the shift. |
|    |  |    | Display a message on the Delivery Ticket stating \$0 due,  |
|    | Contracts 100% Prepaid                 | Υ  | based on the Energy Force Bill Type setup for 100% Prepaid   |
| 30 |  |    | Contracts.   |
|    |  |    |  |
| 31 | Print Customer Term Code on            | N  | Energy Force Customer Terms Code will print on the   |
|    | Invoice?                               |    | invoice with a Payment Due by XX/XX/XX line under the Total.   |
| 32 | Temperature Compensate                 | N  | If marked Y, there will be a Liquid Temp field at the Start Shift  |
|    | Tank %?                                |    | screen that is required to be completed.   |
| 33 | Suppress 'Remove All Taxes'?           | Υ  | An option to disable <b>Remove All Taxes</b> button on the   |
|    |  |    | Invoice screen. If set to N, the driver will have the option to  |
|    |  |    | remove all taxes.  |

| 34 | Display 'View History'?                | Υ | Marked Y the driver has a button on the <i>Tank</i> screen to view 12 months of historical deliveries to the tank; also needs set up in System Settings in Energy Force. |
|----|--|---|--|
| 35 | GPS Service?                           | N | Leave default.   |
| 36 | Collect Regulator Information?         | Υ | Option to allow the driver to add and modify Regulator Information.  |
| 37 | Navigate                               | Υ | Turns on Navigate button for CoPilot.  |
| 38 | Do Not Use                             | N | Do not use.  |
| 39 | Energy Track V2                        | Υ | NoLongerInUse  |
| 40 | Allow Payments                         | N | An option to disable the <b>Payment</b> button, preventing drivers from accepting payments and issuing receipts.   |
| 41 | Allow driver to change leak check date | N | Allows drivers to change Leak Check dates within Energy Track without processing an Out of Gas.  |