Price Setup

Last Modified on 11/01/2023 1:12 pm EDT

Energy Force uses Price Codes and Tier Pricing to determine prices for customers by product. Tier Pricing is structured according to how much product by gallon the customer uses. However, it is not required to use Tier Pricing on all products. One Price Code and Tier can be set up per product. Price Codes can be associated to a Rack Code and automatically updated using Update Rack Pricing. The Price Code is tied to the customer on the *Tank Information* window.

The Total Gallons Used by Price Code report lists the *Customer Number*, *Name*, *Serial Number*, *Price Code Tier*, *Tank Size*, *Total Gallons*, and *Total Sales* by Customer Number and Price Code. This report reflects the Price Code that is currently on the customer's *Tank Information* window. If the Price Code or Tier was changed, it is not listed on the report.

1. To enter a Price Code on the *Price Maintenance* window, choose *Edit/Create*. To change a Price Code, select

the Price Code and make any necessary changes.

2. Enter the Division the Price Code is assigned.

Division	Price Code	Price Description	Price Type	Avgd Price Y/N	Rack Code	Rack Price Description
1	1	RESIDENTIAL	1	No	0	
1	2	COMMERCIAL	0	No	0	
1	3	AGRICULTURAL	0	No	0	
1	4	GASOLINE	0	No	0	
1	5	DYED DIESEL	0	No	0	
1	6	LABOR	0	No	0	
1	7	NO PRICE	0	No	0	
1	8	DEFERRED BILLING DIESEL	0	No	0	
1	99	PREBUY CONTRACT PRICE 2017	0	No	0	
2	1	RESIDENTIAL	0	No	0	
2	2	COMMERCIAL	0	No	0	
2	3	AGRICULTURAL	0	No	0	
2	4	GASOLINE	0	No	0	
2	5	DYED DIESEL	0	No	0	

- 3. In the *Price Code* field, enter a unique identifier for the Price Code. This can be up to three numeric characters.
- 4. In the Price Description field, enter a description for the Price Code.
- 5. The Average Price Y/N is normally defaulted to N. If using the Remote Tank Monitoring buyout program change this to Y.
- 6. In the *Rack Price Code* field, enter the Rack Code associated with the price or press**F5** to select the Rack Code from the list. Leave 0 if the price is not associated with a Rack Code.
- 7. Enter the price for this Price Code in the A Tier field. Continue with B, C, D, etc. as necessary.

Pricing Tiers	Starting Gallons Ending Gallons		Low Cap	High Cap	Margin
A Tier 2.0000	1	100	0.0000	0.0000	0.0000
B Tier 0.9900	101	200	0.0000	0.0000	0.0000
C Tier 0.9800	201	399	0.0000	0.0000	0.0000
D Tier 0.9700	400	499	0.0000	0.0000	0.0000
E Tier 0.9600	500	599	0.0000	0.0000	0.0000
F Tier 0.9500	600	699	0.0000	0.0000	0.0000
G Tier 0.9400	700	799	0.0000	0.0000	0.0000
H Tier 0.9300	800	899	0.0000	0.0000	0.0000

8. In the Starting Gallons field, enter the starting number of gallons to which the price applies.

9. In the Ending Gallons field, enter the ending number of gallons the to which the price applies.

10. Enter the Low Cap for this Price Code. Leave 0 if there will be no low cap for the price.

11. Enter the High Cap for this Price Code. Leave 0 if there will be no high cap for the price.

12. Select Save.